

在 Android 電話 (Samsung) 上設定電子郵件帳號的步驟：

1. 在主畫面上選擇 <電子郵件>





**UDomain Web Hosting Company Ltd.**

18/F., Kinox Centre, 9 Hung To Road,  
Kwun Tong, Kowloon


Tel (852) 2554 7545

Fax (852) 2554 7215

Email [service@udomain.hk](mailto:service@udomain.hk)

Website [www.udomain.hk](http://www.udomain.hk)

**2. 點選 <其他>**





**UDomain Web Hosting Company Ltd.**

18/F., Kinox Centre, 9 Hung To Road,  
Kwun Tong, Kowloon

Tel (852) 2554 7545

Fax (852) 2554 7215

Email [service@udomain.hk](mailto:service@udomain.hk)

Website [www.udomain.hk](http://www.udomain.hk)

3. 電子郵件地址：輸入電子郵件地址 (例：user@example.com)
4. 密碼：輸入電子郵件帳號密碼
5. 按 <登入>

A screenshot of a mobile application interface for account setup. The screen is titled '設定帳戶' (Set Account) with a back arrow. It features two input fields: '電子郵件地址' (Email Address) and '密碼' (Password). Below the password field is a radio button labeled '顯示密碼' (Show Password). At the bottom, there are two buttons: '手動設定' (Manual Setup) and '登入' (Login). A keyboard is visible at the bottom of the screen, with the '@' symbol selected in the bottom row. The status bar at the top shows the time 14:17 and 100% battery.




**UDomain Web Hosting Company Ltd.**

18/F., Kinox Centre, 9 Hung To Road,  
Kwun Tong, Kowloon

Tel (852) 2554 7545  
Fax (852) 2554 7215  
Email [service@udomain.hk](mailto:service@udomain.hk)  
Website [www.udomain.hk](http://www.udomain.hk)

**6. 點選 <IMAP 帳號>**





**UDomain Web Hosting Company Ltd.**

18/F., Kinox Centre, 9 Hung To Road,  
Kwun Tong, Kowloon

Tel (852) 2554 7545  
Fax (852) 2554 7215  
Email [service@udomain.hk](mailto:service@udomain.hk)  
Website [www.udomain.hk](http://www.udomain.hk)

7. 電子郵件地址：輸入電子郵件地址 (例：user@example.com)
8. 用戶名稱：再次輸入電子郵件地址 (例：user@example.com)
9. 密碼：輸入電子郵件帳號密碼
10. IMAP 伺服器：輸入 <域名 ( 除去"點" )>.securemail.hk
11. (例：examplecom.securemail.hk)
12. 安全性類型：點選 <SSL (接受所有證書)>
13. 連接埠：輸入 993

A screenshot of the '伺服器設定' (Server Settings) screen in the UDomain mobile app. The screen is in Chinese and shows a form for configuring an email account. At the top, there is a back arrow and the title '伺服器設定'. Below this, there are sections for '帳戶' (Account) and '內送伺服器' (Incoming Server). The '帳戶' section includes fields for '電子郵件地址' (Email Address), '用戶名稱' (Username), and '密碼' (Password). A red error message '輸入的電子郵件地址或密碼錯誤。' (Entered email address or password is incorrect.) is displayed below the password field. There is a toggle switch for '顯示密碼' (Show Password). The '內送伺服器' section includes a field for 'IMAP 伺服器' (IMAP Server), a dropdown menu for '安全類型' (Security Type) currently set to 'SSL', and a field for '端口' (Port). At the bottom, there is a field for 'IMAP 路徑首碼' (IMAP Path Prefix) and a red '登入' (Login) button. The bottom navigation bar shows a hamburger menu icon, a home icon, and a back arrow.

14. 往下滑到外寄伺服器
15. SMTP 伺服器\*：輸入 **ud.1025.hk**
16. 安全性類型：點選 <TLS (接受所有證書)> 或 <無>
17. 連接埠：輸入 **1025**
18. 使用者名稱：再次輸入電子郵件地址 ( 例：**user@example.com** )
19. 密碼：輸入電子郵件帳號密碼
20. 點選 <登入> 及 <完成>



14:20 99%

< 伺服器設定

SSL ▾

端口

IMAP 路徑首碼  
可選

外寄伺服器

SMTP 伺服器

安全類型

SSL ▾

端口

需要認證才可發送電子郵件

用戶名稱

密碼

顯示密碼

登入

||| ○ <



**UDomain Web Hosting Company Ltd.**

18/F., Kinox Centre, 9 Hung To Road,  
Kwun Tong, Kowloon

Tel (852) 2554 7545

Fax (852) 2554 7215

Email [service@udomain.hk](mailto:service@udomain.hk)

Website [www.udomain.hk](http://www.udomain.hk)

